

## **MUMS Setup does not RUN**

If after running SETUP from the MUMS-CD folder nothing happens, then it might be a conflict of the version of Windows. Some versions of Windows 11 will not run SETUP.

In this case if you are trying to setup a new MUMS workstation, do the following:

- Copy the C:\MT2000 folder from an existing workstation.
- Copy this to the new workstation.
- Run BDEINSTSQL.exe from the MUMS-CD folder that you created in prior instructions.
- Accept all default answers.
- Copy the IDAPI32.CFG from an existing workstation that would be found normally under the C:\BDE32 folder to the following:
  - C:\Program Files (x86)\Borland\Common Files\BDE
- Create a shortcut on desktop by right clicking on C:\MT2000\MT2000.exe